


JAPAN SCENERY DISK

1. Tokyo
2. Osaka



SUBLOGIC
SCENERY
DISK

APPLE II, II plus, IIfx, IIfx

For use with JET and with FLIGHT SIMULATOR
(Version 2.0 ONLY).

JAPAN

subLOGIC Japan Scenery Disk

Tokyo & Osaka Area

Database Design by Michael Woodley

© 1986 SubLOGIC Corporation

First Edition

First Printing

All Rights Reserved

SubLOGIC Corporation

713 Edgebrook Drive

Champaign, IL 61820

Japan Scenery Disk

Introduction

SubLOGIC Scenery Disks are an enhancement designed to expand the potential flying environment of Flight Simulator II and other SubLOGIC flight simulation programs. You must have Flight Simulator II, Microsoft Flight Simulator, or Jet in order to use a Scenery Disk.

This Japan Scenery Disk (SD) covers the area from Tokyo to Osaka in great detail, and is appropriate for both visual flight sight-seeing and VFR or IFR cross-country navigation. Highlights of the Japanese scenery area include a highly-detailed rendition of downtown Tokyo (with Tokyo Tower, Palace grounds, and canal network), Mt. Fuji, the Shin Kansen bullet train network, and Osakajo castle. All mountains, lakes, and waterways are accurately located. All airports are highly detailed; many include towers and refueling facilities. Many VOR and NDB transmitters are also included. The flying environment of this SD is shown on the accompanying chart.

If you fly off of the scenery area depicted in this Japan SD chart, you will enter the default Japan database and eventually fly out of range of all radio aids.

Reading a Sectional Directory

This Japan SD sectional directory lists all available airports in alphabetical order, followed by all radio-nav aids. Each airport listing includes a detailed diagram of the airport as it appears on the disk. Airport and radio-nav aid listings are organized as follows:

1—2 - ALBUQUERQUE AND EL PASO—2

(Airport Diagram)

3—Alpine

4—12628N 10661E—5
6—alt. 4513
7—RWY 1-19 8—5999 X 72
RWY 5-23 4821 X 39

9—Anton Chico (VOR)—10

4—14710N 10537E—5
11—freq. 110

9—Artesia (NDB)—10

4—13703N 10575E—5
11—freq. 414

- | | |
|----|---------------------------|
| 1 | Page number |
| 2 | Sectional name |
| 3 | Airport name |
| 4 | North coordinate |
| 5 | East coordinate |
| 6 | Altitude in feet |
| 7 | Runway Designator, number |
| 8 | Runway dimensions in feet |
| 9 | Radio Aid name |
| 10 | Radio Aid type designator |
| 11 | Radio Aid frequency |

The vertical sides of each airport diagram align with magnetic north. Magnetic north is the direction you are pointing when your magnetic compass reads 0. Each sectional map's VOR needles point toward magnetic north. The sides of the map align with true north. This is consistent with NOAA sectionals.

Using this Scenery Disk with Flight Simulator II

Load Flight Simulator II in the usual way. When the program has finished loading, enter the simulator's program editor as described in your operating manual and set the NORTH and EAST coordinates of the airport you've chosen from the directory for the region you'd like to explore (set ALTITUDE to 0). Exit the editor, remove the FS2 disk and insert the Japan Scenery Disk. Next, press CTRL E and wait for a menu to appear. This menu page lists the names of the sectionals included on the Scenery Disk. Press any key to exit, and you should find yourself at the airport you've selected. If no scenery is visible, go into radar mode and zoom out to determine your approximate location. You should be able to zoom all the way out and view the entire Japan database, complete with coastal outlines. Re-enter the program editor and double-check your coordinates, making sure that both NORTH and EAST coordinates are correct.

When you find yourself at the airport you've selected, it may be a good idea to save your position to a User Mode (see User Mode Library in the FS2 Pilot's Operating Handbook). This way, if you crash, you will be returned to the selected airport. Otherwise you will be returned to a preset location far away from the Japan scenery area.

IMPORTANT - If you want to change Scenery Disks or go back to the scenery on the FS2 disk, you must log-in the new disk by pressing CTRL E. If you do not log-in the new disk, you will not get the new scenery and you will risk causing a disk load error.

Using a Scenery Disk with Microsoft Flight Simulator (IBM PC Versions)

Load Flight Simulator in the usual way. When you want to switch to a Scenery Disk, remove the Flight Simulator disk and insert the appropriate Scenery Disk. Press CTRL E. This will log-in the disk. A message will appear on the screen identifying the names of the sectional areas contained on the disk.

The first Scenery Disk log-in automatically checks to see if you have the most recent version of Flight Simulator. If you don't, the program updates Flight Simulator in memory. When this happens, your flight coordinates are set back to the Chicago area. This will only happen on the first Scenery Disk log-in of the session. After the first log-in, your flight coordinates and conditions will carry over as you change Scenery Disks while flying.

After logging in the first Scenery Disk, you can fly or slew through all of the scenery on the disk. You can freely exchange Scenery Disks as you fly to new areas. Press CTRL E to log-in the new area when you switch disks. If you fail to log-in a new Scenery Disk after inserting it, it will be automatically logged in when the disk is accessed. The log-in message will appear after every manual or automatic log-in.

Using the Microsoft Flight Simulator Disk as a Scenery Disk

The Flight Simulator disk contains all of the usual scenery for the Chicago, Seattle, Los Angeles, and New York areas. You can insert this disk and log it in as you would any other Scenery Disk to fly in these areas. This applies to Jet as well as Flight Simulator.

Special Note for IBM PC Flight Simulator Version 2.0

Very few copies of Version 2.0 exist. You most likely have Version 2.1, 2.10, 2.10a, 2.12, or a later version of Microsoft Flight Simulator. Look on the disk label near the serial number area, or look on the first menu page when loading Flight Simulator. If you have Version 2.0, insert the Scenery Disk and press ESC instead of CTRL E for the first log-in of the session. After this first log-in, press CTRL E as usual to log-in new Scenery Disks. Also, never re-insert the Version 2.0 disk to use the Chicago, Seattle, Los Angeles, or New York scenery; you must re-boot Version 2.0 to return to these areas. Version 2.0 also cannot be used as a Scenery Disk for Jet.

Tandy 1000/1200/2000 Flight Simulator

Scenery Disks are compatible with the Tandy 1000/1200/2000 version of Flight Simulator. With this version, always make sure to log-in a new Scenery Disk by pressing CTRL E once the disk has been inserted. No auto-load is available on this version, and failure to log-in a new disk can cause unpredictable results when the disk is accessed after an unlogged disk change.

Special Note for Compaq 286 Users

The 1.2Mbyte floppy drives in the Compaq Deskpro 286 computer cause disk-read errors when using Scenery Disks with SubLOGIC Jet or Microsoft Flight Simulator. Here is the reason why, and how to get around it:

PROBLEM - Whenever you remove a disk from the floppy drive by turning the release lever, the diskette springs out of the drive. This spring action triggers a switch in the drive that informs the disk read/write software that you have just changed the disk. The software assumes that you are about to insert a new disk, and switches to 1.2Mbyte read mode from whatever mode it happens to be in. Jet, Flight Simulator, Scenery Disks (and many other manufacturers programs) are on 360K disks, and a read error results when the Compaq 286 tries to read them as 1.2Mbyte disks.

You can verify this for yourself using the Microsoft Flight Simulator. Boot the disk, then enter and exit the editor several times (ESC key) just to see that everything is functioning properly. Then pop the disk out of the drive, re-insert it, and try to get back into the program editor. You will get a disk read error.

SOLUTION - You can avoid this problem by tricking the disk drive into thinking that you haven't changed disks. Do this by holding the disk in place with your finger while releasing the disk-release lever. **DON'T LET THE DISK POP OUT OF THE DRIVE.** Then manually remove the disk and insert a Scenery Disk (or Flight Simulator as scenery for Jet). The computer will never know that you changed the disk, and everything should work fine. Remember - if you let the disk pop itself out of the drive, the switch will be activated and the drive will go into 1.2Mbyte mode, thus creating errors.

Jet Users


Scenery Disks are compatible with SubLOGIC Jet. Follow the instructions in your Jet manual for loading a Scenery Disk. Jet has no automatic log-in feature, so always make sure you return to the Jet startup menu page before inserting a new Scenery disk. Changing Scenery Disks in the middle of a Jet flight can cause unpredictable results when the disk is accessed after a disk change.

Conclusion

We intend to periodically update and improve our Scenery Disks to include more airports, radio aids, and scenery details as recommended by users. If you know of an airport (or any other detail) that should be included on future versions of these Scenery Disks, please drop us a line and include the required information ON A SEPARATE SHEET OF PAPER (so we can store it in our files). Here's what we need to know:

Airports:	NAME, CITY, & STATE
	LATITUDE, LONGITUDE, & ALTITUDE
	HEADING, LENGTH, & WIDTH of each runway
Buildings, objects:	NAME, CITY, & STATE
	LATITUDE, LONGITUDE, & DIMENSIONS

Pictures and postcards are also welcome, especially aerial views. If you're unable to determine the latitude and longitude for the object or airport in question, please provide a description of where the object can be located on a map. All customer correspondence is read and answered (when appropriate). And please; remember to include any scenery suggestions or information on a SEPARATE page of your letter.



Atsugi


18118N 32707E
Alt. 205

RWY 1-19 8000 X 150

ILS 1

FREQUENCY:	111.3
HEADING:	7
ALTITUDE:	1500 @ 4.1 DME

2 - JAPAN




Gifu

17714N 31890E
Alt. 128

RWY 10-28

8860 X 150



Hamamatsu


17584N 32274E

Alt. 151

RWY 9-27

8366 X 197


4 - JAPAN



Hyakuri

18542N 32874E
Alt. 104

RWY 3-21 8860 X 150




Iruma

18262N 32619E
Alt. 299

RWY 17-35

6562 X 148

6 - JAPAN



Komatsu

18042N 31572E
Alt. 18

RWY 6-24 8860 X 150

ILS 6

FREQUENCY:	110.1
HEADING:	61
ALTITUDE:	1084 @ 3.7 DME




Matsumoto

18170N 32090E
Alt. 2155

RWY 18-36 4920 X 100

8 - JAPAN



Nagoya


17669N 31932E
Alt. 52

RWY 16-34

9000 X 150

ILS 34

FREQUENCY:	111.7
HEADING:	339
ALTITUDE:	2312 @ 8.4 DME



New Tokyo Int'l (Narita)

18375N 32940E
Alt. 139

RWY 16-34 13123 X 200


ILS 16

FREQUENCY:	111.1
HEADING:	156
ALTITUDE:	1461 @ 3.9 DME

ILS 34

FREQUENCY:	111.9
HEADING:	336
ALTITUDE:	1678 @ 4.5 DME

10 - JAPAN



Osaka Int'l

17267N 31528E
Alt. 49

RWY 14L-32R	6000 X 150
RWY 14R-32L	9840 X 200



Shimofusa


18334N 32819E
Alt. 98

RWY 18-36 7380 X 200

ILS 18

FREQUENCY:	109.1
HEADING:	186
ALTITUDE:	1998 @ 6.3 DME

12 - JAPAN




Tokyo Int'l (Haneda)

18201N 32787E
Alt. 12

RWY 4-19	8200 X 150
RWY 15L-33R	10335 X 200
RWY 15R-33L	9840 X 150

ILS 33R	FREQUENCY:	110.9
	HEADING:	332
	ALTITUDE:	2966 @ 10.5 DME




Yao

17220N 31616E
Alt. 33

RWY 9-27	4890 X 150
RWY 13-31	3940 X 100

14 - JAPAN



Yokota

18217N 32618E
Alt. 457

RWY 18-36 11000 X 200

ILS 36

FREQUENCY:	109.7
HEADING:	357
ALTITUDE:	2114 @ 7 DME

Aichi (NDB)

17633N	31976E
freq.	397

Akeno (NDB)

17347N	31988E
freq.	380

Ami (VOR)

18451N	32839E
freq.	116

Atsugi (NDB)

18119N	32711E
freq.	265

Chigasaki (NDB)

18055N	32712E
freq.	236

Choshi (VOR)

18427N	33082E
freq.	113.6

Daigo (NDB)

18765N	32751E
freq.	225

Daigo (VOR)

18754N	32749E
freq.	115.3

16 - JAPAN

Eda (NDB)

18172N	32716E
freq.	357

Fukui (NDB)

17930N	31549E
freq.	400

Goboh (VOR)

16876N	31573E
freq.	116.9

Hamamatsu (NDB)

17580N	32272E
freq.	229

Hamamatsu (VOR)

17580N	32272E
freq.	114.7

Handeda (VOR)

18202N	32787E
freq.	116.5

Hotaka (NDB)

18216N	32062E
freq.	387

Hyakuri (NDB)

18547N	32877E
freq.	366

Hyakuri (VOR)

18546N 32873E
freq. 113.3

Itami (NDB)

17276N 31516E
freq. 205

Iwaki (VOR)

19002N 32866E
freq. 117.7

Kawakado (NDB)

18289N 32578E
freq. 251

Komatsu (NDB)

18048N 31571E
freq. 234

Komatsu (VOR)

18043N 31569E
freq. 112

Kowa (NDB)

17467N 32025E
freq. 325

Kowa (VOR)

17455N 32042E
freq. 113.5

18 - JAPAN

Kumagaya (NDB)

18372N 32530E
freq. 240

Kushimoto (NDB)

16789N 31875E
freq. 275

Kushimoto (VOR)

16792N 31879E
freq. 112.9

Matsumoto (VOR)

18167N 32095E
freq. 117.6

Miyakejima (NDB)

17594N 32995E
freq. 260

Miyakejima (VOR)

17602N 32970E
freq. 117.8

Miyazu (VOR)

17503N 31318E
freq. 112.6

Moriya (VOR)

18382N 32785E
freq. 114

Nagoya (NDB)

17666N 31933E
freq. 360

Nagoya (VOR)

17671N 31928E
freq. 114.2

Nanki-Shirahama (NDB)

16816N 31698E
freq. 394

Narita (VOR)

18376N 32940E
freq. 117.3

Nasu (VOR)

18720N 32643E
freq. 114.8

Nikko (NDB)

18579N 32643E
freq. 389

Onjuku (VOR)

18151N 33049E
freq. 115.7

Osaka (NDB)

17247N 31588E
freq. 340

20 - JAPAN

Osaka (VOR)

17270N	31541E
freq.	113.9

Oshima (NDB)

17813N	32830E
freq.	216

Oshima (VOR)

17812N	32830E
freq.	113.1

Oshima Airport (NDB)

17843N	32800E
freq.	392

Otsu (NDB)

17436N	31631E
freq.	368

Otsu (VOR)

17416N	31620E
freq.	117.1

Rankin (NDB)

18131N	32677E
freq.	379

Sakura (NDB)

18338N	32890E
freq.	350

Sakura (VOR)

18366N 32901E
freq. 112.7

Sekiyado (VOR)

18391N 32727E
freq. 117

Shinoda (NDB)

17153N 31584E
freq. 219

Shinoda (VOR)

17155N 31587E
freq. 112.3

Shizuhama (VOR)

17696N 32452E
freq. 109.2

Tachikawa (NDB)

18251N 32630E
freq. 330

Tateyama (NDB)

18003N 32927E
freq. 373

Tateyama (VOR)

17986N 32942E
freq. 112.5

22 - JAPAN

Tokushima (VOR)

16897N 31367E
freq. 114.9

Tottori (NDB)

17391N 30998E
freq. 349

Toyama (NDB)

18250N 31774E
freq. 354

Yao (NDB)

17217N 31618E
freq. 386

Yokosuka (NDB)

18041N 32806E
freq. 270

Yokosuka (VOR)

18060N 32787E
freq. 116.2

Zama (NDB)

18156N 32659E
freq. 401

SubLOGIC Scenery Disks expand the potential flying environment of SubLOGIC flight simulation products. You must have Flight Simulator II, Microsoft Flight Simulator, or Jet in order to use a Scenery Disk.

Twelve separate Scenery Disks cover the entire continental United States. Additional Scenery Disks covering other areas of the world are also available. Each disk covers a geographical region of a country, and includes the major airports, radio-nav aids, cities, highways, rivers, and lakes located in that region. Enough detail is available on each disk for either visual or instrument cross-country navigation.


STAR Scenery Disks cover smaller areas with a relatively dense amount of scenery. STAR Scenery Disks are primarily intended for visual flight sight-seeing. They include buildings and landmarks, as well as detailed renditions of all major airports in the area.



subLOGIC

Corporation
713 Edgebrook Drive
Champaign IL 61820
(217) 359-8482 Telex: 206995

Order Line: (800) 637-4983
(except in Illinois, Alaska, and Hawaii)



- | | | |
|--|---|--|
| 1. Dallas-Ft. Worth
Houston
San Antonio
Brownsville | 5. Salt Lake City
Cheyenne
Denver | 9. Chicago
St. Louis
Cincinnati |
| 2. Phoenix
Albuquerque
El Paso | 6. Omaha
Wichita
Kansas City | 10. Billings
Twin Cities
Green Bay |
| 3. San Francisco
Los Angeles
Las Vegas | 7. Washington
Charlotte
Jacksonville
Miami | 11. Lake Huron
Detroit |
| 4. Klamath Falls
Seattle
Great Falls | 8. Memphis
Atlanta
New Orleans | 12. Halifax
Montreal
New York |

ISBN 1-55602-013-9



A2-SD13

JAPAN